

How to use enso (and crest, and xtb)

Setup xtb, crest, and enso

If you have access to the rwth0425 computation project on CLAIX18, then you can skip most of this part, as this installation is ready to go after initialising the software from this project (see at the end). If you want to know more, then read on.

Bundle the programs

The most recent versions this guide is based on are xtb 6.2 RC2, crest 2.7.1, and enso 1.2. I have combined these into one loadable module in the following way:

1. Obtain the distributed archives from the Mulliken Center for Theoretical Chemistry. Currently this should be the following three files: `xtb-190806.tar.xz`, `crest_2.7.1.zip`, `enso.tgz`.
2. Unpack the xtb archive. This will yield the following directories: `bin`, `include`, `lib`, `man`, `python`. There are two configuration files, too, which you can ignore for the moment: `Config_xtb_env.bash`, `Config_xtb_env.csh`.
3. Unpack the crest archive, which only contains crest, and copy it to the `bin` directory. Make sure the executable bit is set.
4. In the root directory, I created the folder `scripts` for enso. This is basically how the setup used to be with xtb, so I kept that part. In principle you could also use a different name or the `bin` directory. Extract the enso archive to this folder. For easier access I have created a symbolic link for enso:

```
ln -s enso.py enso
```

5. Now you have to make the software accessible to run. If you are using `runxtb.bash` (from this repository) follow the installation guide there. If you want to run it only interactively, **source** the appropriate configuration file `Config_xtb_env.*sh` from your respective shell configuration. This will set or append the environment variables `PATH`, `XTBPATH`, `MANPATH`, `LD_LIBRARY_PATH`, `PYTHONPATH`. You need to edit this file to make sure to also include the directory created in 4. in `PATH`. If you are using modules, then you probably know how to create one yourself and how to load it. (In a later version I will include an example.)

Additional notes on enso

1. You will need the `.ensorc` file with standard settings in your home (`$HOME`) directory. Alternatively you can put it in your working directory. (If you are using the bundled versions of me, see above, you will find it in `$XTBPATH/scripts`.) You will need to edit this with settings appropriate

for your system, especially the paths to the executables and external programs.

2. You need a working installation of either ORCA or Turbomole for enso. If you use `runxtb.bash` with modules, you can simply add these to be loaded at runtime. (Note: I have not managed to get it to work with turbomole correctly.)
3. In case you use Turbomole, you also need the `.cefinerc` file in your home/working directory. (If you are using the bundled versions of me, you will find it in `$XTBPATH/scripts`.) You also need to set `PARA_ARCH=SMP` and `PARNODES=<INT>` and export them, for example, include the following line in `.bashrc`:

```
PARA_ARCH=SMP; PARNODES=1; export PARA_ARCH PARNODES
```

Automatically generate NMR Spectra (run enso)

This How-to focusses on the use with this repository, but it can easily be adjusted to interactive use. It is based on a guide from an older version of enso, and it worked with what I have installed. However, there is absolutely no guarantee for correctness.

0. Generate a structure, for example butan-2-one with Open Babel:

```
obabel -: 'CC(=O)CC' --gen3d -oxyz -Ostart.xyz
```

1. Optimise the structure with `xtb` at the same settings as you intend to use `crest` with. This is recommended as `crest` uses this structure for sanity checks, but not strictly necessary.

Note that the double dashes `--` devide the options for `runxtb` from the options send to `xtb` (or `crest`, or `enso`).

```
runxtb -- <XYZ> --opt --gbsa <SOLVENT>
```

2. Set up to generate a conformer-rotamer-ensemble (CRE) with `crest`. This will only take a `<XYZ>` (if found `xtbopt.xyz`), convert it to a `coord`, and puts it into a directory called `crest`.

```
crest.prepare
cd crest
```

3. (optional) Check for tautomers (requires `crest 2.7`).

```
runxtb -S -C crest -- -tautomerize -gbsa <SOLVENT> -chrg <INT> -uhf <INT>
```

This step is still quite fast and submission probably not necessary. If you find some tautomers, then you may want to calculate a spectrum for each of them.

4. Generate CRE (if you did 3, this will [currently] overwrite your output file).

```
runxtb -S -C crest -- -nmr -gbsa <SOLVENT> -chrg <INT> -uhf <INT>
```

5. Run the enso script to get your settings.
You will need either `$HOME/.ensorc` or `./ensorc` for this.

```
runxtb -C enso -o stdout
```

This is very fast and doesn't need submission. The output should go to the terminal, so you can check it easily.

6. Most of the times the default (you chose them in the rc file) settings are ok, if not edit the `flags.dat` to your liking.
7. Run enso. This will take time, as multiple calculations will be performed with Orca or Turbomole. This step also needs more memory than any of the others, I recommend at least 1 GB per cpu, which you can set with the `-m` switch to the runxtb script. I am using the Orca interface, and it worked from the command line. However, since Orca uses MPI, the job script must be edited (see below). I tried Turbomole, but couldn't make that work because of solvation in step 3.

This is a workaround for Orca (for now). Create a script, but do not submit it (`-s`):

```
runxtb -s -m <INT> -o enso.runxtb.out -C enso -- -run
```

Now switch the values for tasks and cpus:

```
--ntasks=<INT>          (was)  --ntasks=1
--cpus-per-task=1      (was)  --cpus-per-task=<INT>
```

Remove the `srun` wrapper before the `enso` command; the line should be:

```
enso -run > "enso.runxtb.out" || exit_status=1
```

I don't know the reason, but the orca input generated with enso will use the `omp` value for the `%pal` block, so this needs to be set to a reasonable number. I believe (but am not sure at all) that `omp` multiplied by `maxthreads` should not exceed the number of cpu you have available. I had quite successful runs with `omp: <INT>` (CPU I request) and `maxthreads: 1` in `flags.dat`. Submit the script to slurm:

```
sbatch enso.runxtb.slurm.bash
```

(Alternatively to all of the above on CLAIX18, get an interactive session with `salloc` and run everything interactively.)

8. Run the NMR program. You probably have to specify the measuring frequency (`-mf <INT>`). This should also be very quick.

```
runxtb -o anmr.runxtb.out -C anmr -- -mf <INT>
```

This should create `anmr.dat` for the next step.

9. Plot the spectrum, which is also quick.

```
runxtb -o stdout -C nmrplot.py -- -i anmr.dat -start 0 -end 11
```

If you are unsure about the options, get help:

```
runxtb -o stdout -C nmrplot.py -- -h
```

10. Look at the spectrum. Be happy.

Notes for rwth0425:

Source the paths for the modules from the project (e.g. from your `bashrc`):

```
. ~rwth0425/initialise/init_rwth0425.sh
```

If you are using the `bashrc` from `rwth-tools`, you can also create a symbolic link to the above script in the initialisation script directory.

```
cd ~/local/bash_profile.d/  
ln -s ~rwth0425/initialise/init_rwth0425.sh init_rwth0425.bash
```

The above mentioned `runxtb` script is preinstalled and configured, if you load the `bin` module.

```
module load rwth0425-bin
```

Get a copy of a modified (for this set-up) `.ensorc` to your home,

```
cp ~rwth0425/local/xtb/examples/ensorc "$HOME"/.ensorc
```

or to your current directory (the directory with the CRE):

```
cp ~rwth0425/local/xtb/examples/ensorc ./ensorc
```

(Same applies to `cefinerc`.) Make modifications as appropriate.

This guide was last updated: 2019-08-28.